## **Contents**

S485 Interface Commands and Documentation
Context
Board
Parameters
Command Structure
Limitations
Command List
Duty Cycle Control
Encoder
Temperature
RPM Speed Control

# **RS485** Interface Commands and Documentation

#### **Context**

#### **Board**

This interface is intended, and only compatible with, the custom 410\_LACEP revision of the VESC Controller.

#### **Parameters**

The interface consists of an RS485 physical layer, using one differential pair. The data is transferred on a half-duplex serial UART running at **115200 baud**.

#### **Command Structure**

Each command consists of a *command\_name* and an optional sequence of *args* separated by *whitespace* and terminated with a *newline* (\n).

<command name> <args>\n


All commands return a *response* terminated by a carriage-return and newline (\r\n).

<response>\r\n

Upper/lower case is irrelevant. In case a command ( $\n$ ), does not match any on the list a error *response* will be returned CMD NOT FOUND.

#### Limitations

Preliminary tests have encountered problems running the board on the extremes of the possible range of control. The following figure is the plot of a "VESC Motor Experiment" sweeping the duty cycle from 0% to 100%.



The x-axis is correlated with the duty cycle. The duty cycle is incremented by 2% every 3 seconds. So the start of the usable band is at around 24s, divide by 3, so 8 steps totalling 16%. The upper limit is also identified at 84%. **So the usable duty cycle range is from 16%-84%**.

#### **Command List**

### **Duty Cycle Control**

## **Set Duty Cycle with Ramp**

- Usage: duty <setpoint> <rate>
- Ramps up/down the motor duty cycle at rate %/s with a timestep of 5 milliseconds.
- Response: Expected time to setpoint in seconds
- Example: duty 0.3 0.6 returns 0.500

### **Encoder**

#### **Read Encoder Count**

· Usage: encoder

• Gets current encoder position in degrees

• Response: 216.40

#### **Reset Encoder Count**

• Usage: reset encoder

• Rests current encoder count.

• Response: 0

#### **Temperature**

### **Read Temperature Sensors**

• Usage: temp

• Returns current temperature of motor and MOSFET in degree Celsius, separated by a comma.

# **Read Motor Temperature Sensor**

- Usage: temp motor
- Returns only the motor temperature in degree Celsius.

## **Read MOSFET Temperature Sensor**

- Usage: temp\_mosfet
- Returns only the MOSFET temperature in degree Celsius.

# **RPM Speed Control**

# **Set RPM Speed**

- Usage: rpm <setpoint> <rate>
- Alternative: speed <setpoint> <rate>
- Ramps up/down the motor duty cycle at rate rad/s^2 with a timestep of 5 milliseconds.
- Response: Expected time to setpoint in seconds
- NOTE: The RPM Control loop is also subject to a limited usable range and throughout testing it was less than the duty cycle control. So **this interface is not recommended**